

Functional permissions

Basic access rights are assigned by means of functional permissions. These permissions can be assigned to individual roles on via the [Roles and Permissions](#) screen. These permissions control the visibility of certain tiles on the Start Screen, as well as the access to specific functions.

Functional Permission	Description <i>Affected Feature or Area of User Interface Menu Entry / Tab</i>
Configure Attribute and Groups	Permission to add, edit or delete attributes . Be aware that users without this permission can still edit attribute values. Permission to add, edit or delete attribute groups and to control edit rights. <i>Administration / Attributes</i> <i>Administration / Attribute Groups</i>
Configure iteraplan	Permission to edit the configuration of iteraplan. <i>Administration / System</i>
Configure Plugin API	Permission to create, edit, delete and run plugins of the plugin API . Be aware that plugin scripts can access all data, independant of what user created the script or executes it. <i>Administration / Plugin API</i>
Create, Update and Delete public Saved Queries	Permission to edit, create & delete public saved queries . <i>Report / Saved queries</i>
Edit Customization	Permission to edit the customizing of iteraplan. <i>Administration / Customizing</i>
Edit Roles and Grant Permissions	Permission to manage roles and permissions . <i>Administration / Roles and Permissions</i>
Execute Bulk Updates	Permission to execute bulk updates/mass updates via the Multi Mode . <i>Lists / Multi Mode</i>
Execute iteraQL Power Queries	Permission to use the query console to execute iteraQL power queries. Note that this permission does not control iteraQL queries via the REST API. <i>Reports / Query Console</i>
Manage ISM Data	Permission to manage Information Security Management(ISM). <i>Security / Requirements / Risks / Actions / Settings</i>
Manage Surveys	Permission to create/edit/delete surveys . <i>Administration / Surveys</i>
Manage Users	Permission to manage users . <i>Administration / Users</i>
Run import and export	Permission to import and export data. <i>Report / Export/Import</i>
Share Saved Queries	Permission to share saved queries (only for visualizations) <i>Report / Saved queries</i>
Subscribe to Building Blocks and view all personal subscriptions	Permission to subscribe to element changes and view your personal subscriptions. <i>Lists / Subscribers</i>
Supervising Data	Permission to delete all comments on building blocks. <i>Single element view / Comments</i>
Use Custom Dashboard	Permission to use custom dashboards . <i>Report / Custom Dashboard</i>

Use Diagram Builder	Permission to access the Diagram Builder . <i>Visualize / Diagram Builder</i>	
Use Global Search	Permission to run global search on building blocks. <i>Start / Search input box</i>	
Use Graphics Reactor	Permission to access and use the iteraplan Graphics Reactor . <i>Report / Graphics Reactor</i>	
Use Navigator	Permission to access the Navigator . <i>Visualize / Navigator</i>	
Use Visualizations	Permission to use all built-in visualizations <i>Visualize / <all diagram types></i>	
View all subscribers of a Building Block	Permission to view subscribers of a building block. <i>Lists / Subscribers</i>	
View History	Permission to view a building block's history. <i>Single element view / History tab</i>	
View Roles and Permissions	Permission to view roles and permissions . <i>Administration / Roles and Permissions</i>	