

Functional permissions

Basic access rights are assigned by means of functional permissions. These permissions can be assigned to individual roles on via the [Roles and Permissions](#) screen. These permissions control the visibility of certain tiles on the Start Screen, as well as the access to specific functions.

Functional Permission	Description <i>Affected Feature or Area of User Interface Menu Entry / Tab</i>
Configure attribute groups	Permission to add, edit or delete attribute groups and to control edit rights. Be aware that users without this permission can still change the attribute group of attributes individually if they are allowed to Configure attributes . <i>Administration / Attribute Groups</i>
Configure attributes	Permission to add, edit or delete attributes . Be aware that users without this permission can still edit attribute values. <i>Administration / Attributes</i>
Public Saved queries	Permission to edit, create & delete public saved queries . <i>Report / Saved queries</i>
Configure iteraplan System	Permission to edit the configuration of iteraplan. <i>Administration / System</i>
Edit roles and grant permissions	Permission to manage roles and permissions . <i>Administration / Roles and Permissions</i>
Execute iteraQL power queries	Permission to use the query console to execute iteraQL power queries. Note that this permission does not control iteraQL queries via the REST API. <i>Reports / Query Console</i>
Use visualizations	Permission to use all built-in visualizations <i>Visualize / <all diagram types></i>
Manage users	Permission to manage users . <i>Administration / Users</i>
Use Navigator visualization	Permission to access the Navigator . <i>Lists Single Element View / Navigator</i>
Execute Bulk Updates	Permission to execute bulk updates/mass updates via the Multi Mode . <i>Lists / Multi Mode</i>
Run import and export	Permission to import and export data. <i>Report / Export/Import</i>
Run global search on Building Blocks	Permission to run global search on building blocks. <i>Start / Search input box</i>
Use Graphics Reactor	Permission to access and use the iteraplan Graphics Reactor . <i>Report / Graphics Reactor</i>
Subscribe to Building Blocks and view all personal subscriptions	Permission to subscribe to element changes and view your personal subscriptions. <i>Lists / Subscribers</i>
Supervising Data	Permission to delete all comments on building blocks. <i>Single element view / Comments</i>
View all subscribers of a Building Block	Permission to view subscribers of a building block. <i>Lists / Subscribers</i>

View History	Permission to view a building block's history <i>Single element view / History tab</i>
Manage Surveys	Permission to create/edit/delete surveys <i>Administration / Surveys</i>